# REXduino – Arduino microcontroller in the REXYGEN system

User guide

Jaroslav Sobota


Version 2.0.0

# Contents

1	Intr	Introduction							
2	Installation								
	2.1	Preparing the slave device	3						
	2.2	Preparing the master device							
	2.3	Using REXduino	5						
		2.3.1 Communication status	6						
	2.4	Example projects	7						
	2.5	Using the REXduino library in REXYGEN	7						
3	Pin modes								
	3.1	Digital out - O	8						
	3.2	Digital out - Q							
	3.3	Digital input - I							
	3.4	Digital input with pullup - J	8						
	3.5	Analog out (PWM) - P	9						
	3.6	Analog in - A	9						
	3.7	Counter - C	9						
	3.8	Encoder - E	9						
	3.9	OneWire - W	9						
4	Communication protocol								
	4.1	Commands	11						
	4.2	Responses							
5	Tro	ubleshooting	13						

### Introduction

The symbiosis of REXYGEN<sup>1</sup> and an Arduino board is based on a simple communication protocol, whose slave part is implemented in the Arduino while the master part is running in the target device of the REXYGEN system (e.g. Raspberry Pi or laptop or desktop PC running the REXYGEN runtime module). In fact, the Arduino serves only as an input/output unit, the control algorithm is running in the runtime module of REXYGEN (RexCore). The Arduino is connected using the USB cable.




<sup>1</sup>www.rexygen.com

# Installation

### 2.1 Preparing the slave device

The Arduino must be programmed first to act as REXduino slave. For that, you have to:

- 1. Open the REXduino\_slave.ino sketch in Arduino IDE.
- 2. Compile it.
- 3. Program Arduino with it.



#### 2.2 Preparing the master device

The master part of REXduino requires only the REXYGEN runtime module (RexCore) to run. See the *Getting started with REXYGEN* user guides at www.rexygen.com for instructions.

Apart from the runtime module only a system driver for the Arduino USB port is required for the Arduino to appear as a serial device


- Windows the driver is part of the Arduino IDE installation
- Raspberry Pi the driver is included in the Raspbian distribution by default

You only need to know the serial port identifier. In Windows it will be e.g. COM4, COM7, etc. In Linux the device will be most probably /dev/ttyACMO or /dev/ttyUSBO but the numbers in the identifiers may differ.


#### 2.3 Using REXduino

The so-called masked subsystems are prepared for you in a library to include Arduino in your projects almost instantly.


A simple setup to start with might include 3 LED lights and 3 resistors:



And the corresponding project in REXYGEN follows:



The working modes of the individual input/output pins must be defined upon double-clicking the Arduino mask in REXYGEN Studio development environment. Also the serial device to use must be specified.



As soon as you compile the project and download it to the target device, the communication with Arduino will be initialized and the LEDs will start to blink.

In the background, the REX duino master sends commands to the Arduino to initialize communication, switch pins to the corresponding modes and read/write data.

#### 2.3.1 Communication status

There are 4 states of the communication with the Arduino:

- 0: Arduino not responding, waiting for timeout to try again
- 1: Serial port open, trying to initialize communication

- 2: Communication initialized, setting pin modes
- 3: Arduino OK, pin modes set, data valid

### 2.4 Example projects

Examples can be found in the Examples folder. Always open the \*\_exec.mdl file, which is the project main file.

#### 2.5 Using the REXduino library in REXYGEN

The files REXduino\_library.mdl and REXduino\_master.c must be placed in one of the locations below:

- the project folder
- ullet the folder defined by the  ${\it LibraryPath}$  parameter of the PROJECT block included in the project
- the folder defined in the Global library path in REXYGEN Studio (Settings  $\rightarrow$  Program Options)

If you wish to start from scratch, copy and paste the block of your choice from REXduino\_library.mdl.

### Pin modes

#### 3.1 Digital out - O

Digital output, default LOW. Control LEDs, valves, relays, etc.

Bring the control signal to the DOn input of the block, where n is the pin number. Or DO\_An if you are using analog pins as digital outputs.

#### 3.2 Digital out - Q

Digital output, default HIGH. Useful for controlling devices with inverted logic (relay boards, typically).

Bring the control signal to the DOn input of the block, where n is the pin number. Or DO\_An if you are using analog pins as digital outputs.

#### 3.3 Digital input - I

Digital input. Intended for reading a switch, the pin should always be connected to HIGH (5V) or LOW (0V).

The state of the pin can be read from the DIn output of the block, where n is the pin number. Or DI\_An if you are using analog pins as digital inputs.

#### 3.4 Digital input with pullup - J

Digital input. Intended for reading a push button. The pin is connected to LOW (0V) when the button is pressed, otherwise it is drawn to HIGH (5V) by the internal 20k pull-up resistor to avoid a "floating pin". Note the inverted logic.

The state of the pin can be read from the DIn output of the block, where n is the pin number. Or DI\_An if you are using analog pins as digital inputs.

#### 3.5 Analog out (PWM) - P

Pulse-width modulated output. Can be used for dimming LEDs, smooth control of motors etc.

Bring the control signal to the  $DOn_PWM$  input of the block, where n is the pin number. The range is 0 to 255.

#### 3.6 Analog in - A

Analog input. Can be used to read potentiometers, NTC thermistors etc.

The measured value is available at the AIn output of the block, where n is the pin number. The range is 0 to 1023.

#### 3.7 Counter - C

Counter for counting pulses from e.g. water consumption meters. Bring the pulses to pin 2 and the count direction to pin 4 (HIGH=count up, LOW=count down). The rising edges on pin 2 are counted. The mode of pin 4 must be set to Counter DIR.

The same applies for the second counter which is available on pins 3 and 5.

The values of the counters are available at CNT2 and CNT3 outputs.

You have to enable the counter by setting the CNT2E (CNT3E) input to 1.

You can reset the counter by setting the CNT2R (CNT3R) input to 1.

#### 3.8 Encoder - E

Reading encoder signals. Bring the encoder signal A to pin 2 and the encoder signal B to pin 4. Both the rising and falling edges of signal A are counted, the direction is given by the encoder B signal. The mode of pin 4 must be set to Encoder B.

You can also connect another encoder to pins 3 and 5.

The values of the encoders are available at CNT2 and CNT3 outputs.


You have to enable encoder evaluation by setting the CNT2E (CNT3E) input to 1.

You can reset the encoder value by setting the CNT2R (CNT3R) input to 1.


#### 3.9 OneWire - W

Reading 1-Wire temperature sensors. In order to use this mode, you have to enable 1-Wire in the REXduino slave sketch. For that, you must include the OneWire library in your Arduino IDE and uncomment the //#define USE1WIRE line. Compile the sketch with this modification and program it into the REXduino slave device (Arduino).

You can use both powered and parasitic sensors as shown in the wiring example below.



The temperature data is available at the OW\_m\_n output of the block, where m and n are pin numbers. The data must be further processed by the OW\_decompose block and the OW\_sensors\_1\_4 as shown below. The function blocks can be found in the REXduino\_library.mdl file.



The sensors are ordered by their ROM IDs. Maximum 15 sensors in one branch!

# Communication protocol

The following table shows the individual commands of the serial communication. Lower-case versions of the commands are also supported for human-readable communication, which is useful for debugging using the serial line monitor in Arduino IDE. The corresponding port must be selected, the settings are baudrate 57600 and "no line ending".

#### 4.1 Commands

communication initialization							
C 2	;						
switch pin mode							
M nPin	pinMode ;						
analog read (analog input)							
A nPin	;						
PWM write (analog output)							
P nPin	val ;						
read digita	read digital input						
I nPin	;						
set digital	output						
O nPin	val ;						
read 1-wire temperature							
T nPin	;						
read counter or encoder value							
N nCnt	N ;						
reset counter							
N nCnt	R ;						
enable counter							
N nCnt	Ε ;						

Additional commands follow . . .

disable counter									
N	nCnt	D	;						
user data (4-byte)									
U	byte0	byte1	byte2	byte3	;				
user data (16-byte)									
0x04	byte0	byte1	byte2	byte3		byte13	byte14	byte15	;

# 4.2 Responses

initialization acknowledgement										
$^{\mathrm{C}}$	2	;								
pin mode acknowledgement										
M	nPin	pinMode	;							
analog input value										
A	nPin	byteH	byteL	;						
PWM value acknowledgement										
P	nPin	val	;							
digital input value										
Ι	nPin	val	;							
digital output acknowledgement										
O	nPin	val	;							
1-wire temperature measurement status										
${ m T}$	nPin	nStat	;							
1-wire	e temper	ature data								
${ m T}$	nPin	nSens	byteH	byteL	;					
count	er or end	coder data								
N	nCnt	N	wordH, byteH	wordH, byteL	wordL, byteH	wordL, byteL	;			
count	er enable	ed								
N	nCnt	Е	;							
counter disabled										
N	nCnt	D	;							
counter reset										
N	nCnt	R	;							
user data (4-byte)										
U	byte0	· ·	byte2	byte3	;					
user data (16-byte)										
0x04	byte0	byte1	byte2		byte14	byte15	;			
error	$\overline{\operatorname{code}}$									
Е	err	err_sub	;							

# Troubleshooting

• Check if the REXduino slave responds. You can act as REXduino master. In the Arduino IDE, open the serial monitor, set baudrate 57600 and "no line ending" and enter the message

c2

The reply must be C2;

- Start with only one or two signals. If it works, add additional signals one-by-one until you reach the problem.
- If the communication status is 2 and never reaches 3, you are probably trying to read 1-Wire temperature but your REXduino slave was compiled without 1-Wire support. See the 1-Wire pin mode for instructions.
- You can print all the outgoing and incoming serial data to the REXYGEN System log. This will allow you to find the problem. In REXYGEN Studio, go to menu  $Target \rightarrow Configure\ System\ Log\ and\ tick\ Information\ and\ Verbose\ in\ the\ Function block messages box. Afterwards you can open System log <math>Target \rightarrow Show\ System\ Log\ and\ analyze\ the\ serial\ communication.$  It is recommended to use a sampling period of 1 second for such debugging purposes.